

CORRCHECK Release Notes

V1.2.5

- Pitch and Height values in Single Flute Report did not match the description at the beginning of the line – corrected.
- Error in creating Single Flute Report without reference corrected.

V1.2.4

- Add AUTO text next to Auto select reference box in Single Flute measurement page
- Add 'none' to the reference selection list on Single Flute Page of the main screen
- Modify Default Paper thickness for Default reference sets
- Add sample Files to the installer
- Status bar in Main Window re-organized to display full file path
- Display File name in Status bar after loading an image from file.

V1.2.3

- Resize Private Logo in Settings corrected
- WBE line error with older calibration INI files corrected
- Plus button changes Icon when in auto values adding mode

V1.2.2

- Language files updated
- Key de-bounce improved.

V1.2.1

- Added Translations of display Text
- VERIFY capture image enabled again.
- Flute Reference definition on separate Window
 - Including material thickness for every flute
 - Including an explanation images
 - Including additional information
 - Including WBE reference and tolerance
- Single Face Flute measurement page : select Flute from the list.
- WBE Page: select Flute reference
- Save WBE statistics data in Text file with decimal separator defined in the settings window
- Reference values for WBE and Single Flute in PDF Reports
- Updated Manuals in English and German
- Manual Depth measurement shows value in Analysis Screen

V1.2.0

- Corrugating roller function for BOBST version
- Select device if multiple devices have been installed on one PC
- Full Screen option (press F10)
- Japanese Font in Reports

-
- Additional Brightness setting (white, gray, dark gray, black)
 - Improved single flute measurement (especially for B-Flute)

V1.1.0

- SAVE and LOAD original images in .CRR Format
- SAVE Analysis Image in .JPG format
- Add sample images to the installer washboard.crr, singlefaced.crr, crease.crr
- Progress-bar in blue color during calculation
- BOBST version

V1.0.11

- Noise Filter in WBE measurement improved to avoid side effects at the left and right ends

V1.0.10

- Calibration routine adapted for B-flute with deeper references (2.45mm)
- Auto scroll WBE line into Display Window

V1.0.9

- Key de-bounce in WBE mode stronger
- Delete WBE value from Statistic by selecting the item inside the table.

V1.0.8

- B-Flute support in Single Faced (multiple brightness capture)

V1.0.6

- Save Data Icon for WBE saves measurement values into a text file
-